



CISCO	IOS XR	JUNIPER	JUNOS	NOKIA SROS	HUAWEI	HVRP
BASIC						
show	show		show		display	
exit	exit/up		exit all		quit	
run	run		-		-	
end	exit		exit all		return	
include	match		match		include	
... formal ...	display-set		-		-	
reload	request system reboot		admin reboot now		reboot	
GENERAL CONFIGURATION						
show running-config	show configuration		admin display-config		display current-configuration	
show startup-config	-		-		display saved-configuration	
configure terminal	configure / edit		configure		system view	
hostname hostname	system host-name hostname		system name systemname		sysname systemname	
show (after conf change)	show compare		info (after conf change)		-	
commit	commit		admin save		save	
shut down	disable		shut down		shut down	
no shut down	delete interfaces x disable		no shutdown		undo shut down	
no	delete		no		undo	
SHOW						
show clock	show system uptime		show system time		display clock	
show ntp status	show ntp status		show system ntp		display ntp-service status	
show history	show cli history		history		display history-command	
show platform	show chassis fpc		show card, show mda		display device pic-status	
admin show platform	show chassis fpc detail		show card detail, show mda detail		display device	
show environment	show chassis environment		-		-	
show inventory	show chassis hardware		-		-	
admin show environment include PM	show chassis hardware match PSM		show chassis environment power-supply		display power	
show diag	show chassis hardware		show chassis environment		-	
show memory summary	show chassis routing engine		show system memory-pools		display memory-usage	
show processes cpu	show system processes extensive		show system cpu		display cpu-usage	
show users	show system users		show system users		display users	
show version	show version		show version		display version	
show licence	-		-		display licence	
-	show system alarms		show system alarms		display alarm all / active	
-	show chassis alarms		-		-	
show arp	show arp		show router arp		display arp all	
show interface	show interfaces		show router interface		display ip interface	
show interface interface	show interfaces interface		show port port		display ip interface interface	
show interface interface statistics	-		show port port statistics		-	
show interface brief	show interface terse		show router interface summary		display ip interface brief	
show policy-map	show class-of-service interface		show router policy		-	
show policy-map interface	show interfaces queue		-		-	
show route	show route		show router route-table		display ip routing-table	
show route summary	show route summary		show router route-table summary		-	
show route ipv6	show route table inet6.0		show router route-table ipv6		display ipv6 routing-table	
show route-map	show policy		show router policy		display route-policy	
show snmp	show snmp statistics		show snmp counters		display snmp statistics	
show tcp	show system connections		show system connections		display tcp statistics	
show ipv4 traffic	show system statistics		-		display ip statistics	
show protocols	show route protocol		-		-	
show flash	show flash		file (+ dir)		dir flash:	
show filesystem	show system storage		-		dir	
show bfd session	show bfd session		show router bfd session		display bfd session all	
show bfd interfaces location x	-		show router bfd interface		display bfd interface	
show interfaces be x	show interfaces aex		show lag x		display interface Eth-Trunk x	
show interfaces be x details	show interfaces aex details		show lag x detail		-	
-	-		show lag x associations		-	
TSHOOT						
ping ip_address	ping_ip_address		ping_ip_address		ping_ip_address	
traceroute ip_address	traceroute_ip_address		traceroute_ip_address		tracert_ip_address	
debug	debug		debug		debugging	
no debug	undebug all		no debug		undo debugging	
monitor interface interface	monitor interface interface		monitor port port		-	
terminal monitor	monitor start messages		-		terminal monitor /terminal trapping	
terminal monitor disable	monitor stop messages		-		undo terminal monitor	
show tech-support	request support info		admin tech-support		display diagnostic-information	
show logging	show log messages		show log id 99 (all)		display logbuffer	
show controllers interface	show interfaces diagnostic optics interface		-		display controller	
show access-lists	show firewall		show filter ip x		display acl x	
CLEAR						
clear	clear		clear		reset	
clear counters interface	clear interface statistics interface		clear counter interface xx		reset counters interface xx	
clear arp-cache	clear arp		clear router arp		reset arp	
clear cef	-		-		reset ip fast-forwarding	
clear route *	clear ip route		clear router route-adv		reset ip forwarding-table statistic protocol all	
clear access-list counters	clear firewall		clear filter		-	
clear line line	request system logout username		-		-	
OSPF						
show ospf (summary)	show ospf overview		show router ospf status		display ospf brief	
show ospf database	show ospf database		show router ospf database		display ospf lsdb	
show ospf interface	show ospf interface		show router ospf interface		display ospf interface	
show ospf neighbor	show ospf neighbor		show router ospf neighbor		display ospf nexthop	
show route ospf	show route protocol ospf		show router ospf routes		display ip routing-table protocol ospf	
show ospf virtual-links	-		show router ospf virtual-link		display ospf vlink	
show ospf statistics	show ospf statistics		show router ospf statistics		display ospf statistics	
ISIS						
display isis interface	show isis interface		show router isis interface		display isis interface	
show clns neighbor	show isis adjacency		show router isis adjaceny		display isis peer	
show isis database	show isis database		show router isis database		display isis lsdb	
show isis topology	show isis topology		show router isis topology		-	
show isis routes	show isis route		show router isis routes		display isis route	
show isis spf-log	show isis spf log		show router isis spf-log		display isis spf-log	
show isis statistics	show isis statistics		show router isis statistics		display isis statistics	
clear clns neighbors	clear isis adjacency		clear router isis adjacency		-	
clear isis *	clear isis database		clear router isis database		-	
clear isis statistics	clear isis statistics		clear router isis statistics		-	
BGP						
show bgp	show route protocol bgp		show router bgp routes		display bgp routing-table	
show bgp community	show route community		-		-	
show bgp neighbors	show bgp neighbor		show router bgp neighbor		display bgp peer	
show bgp peer-group	show bgp group		show router bgp group		display bgp group	
show bgp summary	show bgp summary		show router bgp summary		display bgp peer	
show route bgp	show route protocol bgp		show router bgp routes		display ip routing-table protocol bgp	
clear bgp	clear bgp neighbor		clear bgp		reset bgp all	
clear bgp next-hop registration	clear bgp neighbor		clear bgp next-hop		-	
MPLS						
show mpls interface	show mpls interface		show router mpls interfaces		display mpls interface	
show mpls ldp summary	show ldp overview		show mpls ldp summary		display mpls ldp all	
show mpls ldp interface	show mpls ldp interface		show router ldp interface		display mpls ldp interface	
show mpls ldp bindings	-		show router ldp bindings		-	
show mpls ldp neighbor brief	show ldp neighbor		show router ldp session		display mpls ldp adjacency	
show rsvp interface	show rsvp interface		show router rsvp interface		display mpls rsvp-te interface	
show rsvp neighbors	show rsvp neighbor		show router rsvp neighbors		display mpls rsvp-te peer	
show rsvp session	show rsvp session		show router rsvp session		display mpls rsvp-te session x	
show rsvp counters	show rsvp statistics		show router rsvp statistics		display mpls rsvp-te statistics global	
MULTICAST						
show mfib/mrib route	show multicast route		show mfib/mrib route		display multicast routing-table	
-	show multicast statistics		-		display multicast flow-statistic	
show pim interface	show pim interfaces		show router pim interfaces		display pim interface	
show pim neighbor	show pim interfaces		show router pim neighbor		display pim neighbor	
show pim group-map	show pim group		show router pim group		-	
show ip mroute rp mapping	show pim rps		show router pim rp		display ip rp-info	
show pim traffic	show pim statistics		show router pim statistics		-	
show mrouting	show mrouting		-		display multicast routing-table	
show igmp interface	show igmp interface		show router igmp interface		display igmp interface	
show igmp groups	show igmp group		show router igmp group		-	
show igmp traffic	show igmp statistics		show router igmp statistics		-	
show mld interface	show mld interface		show router mld interface		display igmp interface	
show mld groups	show mld group		show router mld group		display igmp group	
show mld traffic	show mld statistics		show router mld statistics		-	
VRRP						
show vrrp interface interface	show vrrp interface interface		show router vrrp instance interface		display vrrp interface interface	
show vrrp status	show vrrp brief		-		display vrrp brief	
show vrrp summary	show vrrp summary		-		-	
show vrrp statistics	-		show vrrp statistics		display vrrp statistics	