

BANGLALINK-INTERNET-KBAZAR#show running-config
Building configuration...

Current configuration : 2293 bytes

!

! Last configuration change at 13:22:00 UTC Sat Aug 13 2016 by noc

!

version 15.4

service timestamps debug datetime msec

service timestamps log datetime msec

no service password-encryption

!

hostname BANGLALINK-INTERNET-KBAZAR

!

boot-start-marker

boot-end-marker

!

!

enable password bdcom987

!

aaa new-model

!

!

!

!

!

!

!

aaa session-id common

!

!

!

!

!

!

!

!

!

!

!

ip dhcp excluded-address 192.168.0.1 192.168.0.10

!

ip dhcp pool BL_office


```
description primary_link
ip address 10.255.33.46 255.255.255.252
ip nat outside
ip virtual-reassembly in
duplex auto
speed auto
!
interface GigabitEthernet0/1
ip address pool BL_office
ip nat inside
ip virtual-reassembly in
duplex auto
speed auto
!
router bgp 65526
  bgp log-neighbor-changes
  network 119.40.84.40 mask 255.255.255.252
  neighbor 10.255.33.45 remote-as 24122
  neighbor 10.255.33.45 description BDCOM-Primary
  neighbor 10.255.33.45 remove-private-as
  neighbor 10.255.33.45 prefix-list bdcom-p-in in
  neighbor 10.255.33.45 prefix-list bdcom-p-out out
!
ip forward-protocol nd
!
no ip http server
no ip http secure-server
!
ip nat pool netpool 119.40.84.41 119.40.84.42 netmask 255.255.255.252
ip nat inside source list 100 pool netpool overload
!
!
ip prefix-list bdcom-p-in seq 10 permit 0.0.0.0/0
ip prefix-list bdcom-p-in seq 50 deny 0.0.0.0/0 le 32
!
ip prefix-list bdcom-p-out seq 10 permit 119.40.84.40/30
ip prefix-list bdcom-p-out seq 50 deny 0.0.0.0/0 le 32
!
!
access-list 100 remark ==Control NAT==
access-list 100 permit ip 192.168.0.0 0.0.0.255 any
!
!
```

```
!  
control-plane  
!  
!  
!  
line con 0  
  password bdcom987  
line aux 0  
line 2  
  no activation-character  
  no exec  
  transport preferred none  
  transport output pad telnet rlogin lapb-ta mop udptn v120 ssh  
  stopbits 1  
line vty 0 4  
  password bdcom987  
  transport input telnet  
!  
scheduler allocate 20000 1000  
!  
End
```

```
-----  
ACI-Hobigong(config)#line vt  
ACI-Hobigong(config)#line vty 0 4  
ACI-Hobigong(config-line)#tran  
ACI-Hobigong(config-line)#transport in  
ACI-Hobigong(config-line)#transport input al  
ACI-Hobigong(config-line)#transport input all
```

```
-----For Telnet Allow -----
```

```
10.255.72.22 -ACT Hobigong  
username noc password 0 bdc0m#@!
```